



# Physical Pi

Romilly Cocking romilly@quick2wire.com Steve Freeman steve.freeman@quick2wire.com







http://www.libcary.openn.eds/images/eshibits/mosic/stokowski/50.jp





http://www.dlickr.com/photos/peds/2825693786

http://quick2wire.com/resources

# Barriers to entry have never been lower

http://quick?wire.com/resources

Cheap CAD

Social marketing and design

Crowdfunding

Manufacturers, makers, markets

http://guick?wire.com/resource

### We became makers

because we wanted to get children engaged with physical computing

http://quick2wire.com/resources

## We became makers

because it's a good way to get long-term engagement

## We became makers

because we wanted to ignite the passion

http://quick?wire.com/resource


## We became makers

so that the kids could have a future

http://quick?wire.com/resources

A robot that can explore an unknown area

"C3Pi"





http://quick?wire.com/resource

# **Getting started**

#### Built-in GPIO

- flashing LED
- flashing LED and button
- counting






http://mirktwire.com/resources

```
with pins.pin(1, direction=Out) as led:
  for v in cycle([1,0]):
    led.value = v
    sleep(0.5)
```



```
with pins.pin(0, direction=In) as button,\
    pins.pin(1, direction=Out) as led:
for v in cycle([1,0]):
    led.value = v * button.value
    sleep(0.5)
```




http://quick2wire.com/resources

```
pins = [pins.pin(i, Out) for i in range(8)]
try:
  for p in pins: p.open()

for count in cycle(range(256)):
    for (pin, value) in zip(pins, bitset(count)):
        pin.value = value
        sleep(0.5)

finally:
    for p in pins: p.close()
```




http://quick?wire.com/resources

# $I^2C$


#### More GPIO


- many LEDs, single process
- many LEDS, multiple processes Analogue



```
http://quick?wire.com/resources
```

```
with i2c.I2CMaster() as bus:
    pe = PortExpander(bus, address)
    pe.set_iodir_b(0x00)
    pe.clear_gpio_b()
    try:
        for count in cycle(range(256)):
            pe.set_gpio_b(count)
            sleep(0.1)
        finally:
        pe.clear_gpio_b()
```





```
http://quick?wire.com/resources
```

```
with closing(i2c.I2CMaster()) as master:
    pcf = PCF8591(master, FOUR_SINGLE_ENDED)
    gpio_pins = [pins.pin(i, Out) for i in range(8)]
    display = AnalogueDisplay(1.0, *gpio_pins)
    ain3 = pcf.single_ended_input(3)


for pin in gpio_pins: pin.open()
    try:
    while(True): display.display(ain3.value)


finally:
    display.display(63)
    for pin in gpio_pins: pin.close()
```

http://quick?wire.com/resources

# Pi and \*duino

Drive an LCD





http://quick?wire.com/resource

# Pi, Arduino, and Robot

Drive motors IR Sensor Servo + Ultrasonic Ranger



What worked
Increments
Testing

OCD
http://quickZwire.com/resources
Pairing
http://quick2wire.com/resources
Fun

## What didn't work

http://quick2wire.com/resources

# 1 full-time 8 part-time 7 time zones

http://quick2wire.com/resources

Become a maker

### You can build...

- a robot
- · a weather station
- a 3D printer
- ...

http://quick2wire.com/resources

# Easy, fun, affordable

http://quick?wire.com/resources

## Tomorrow you can...

Reuse designs
Read guides and tutorials
Buy kits and components
Start to catch up with the 12-year olds

